Upgrade introductions (USB-C Cable)


Preparations:

1> Download the tools and extract it, and run 'setup_v2.0.8.exe' to install the necessary tool for Vim upgrading:



Steps as following:

- 1> Open 'USB_Burning_Tool_v2.0.8.exe', click 'File-->Import image' to chose the image for Vim.
- 2> Connect Vim and PC with an USB-C cable, and power on Vim.
- 3> Let Vim enter into upgrade mode to complete the upgrading:
- Long press 'Power' key without release
- Short press 'Reset' key and release
- Count 2-3 seconds and release the 'Power' key to enter into upgrade mode
- 4> Make sure your PC have found Vim device as upgrade mode, then click 'Start' button of the tool to start upgrading:



Tips: Click 'Stop' button first then close the tool to quit upgrading operation.

Have Fun!

See also:

- 1 > Upgrade from a TF card.
- 2> Other methods to enter into upgrade mode.